

At the departure of animals

Step 01

SCRAPING - DRY CLEANING "A good cleaning = 80% of germs eliminated"



- 1 Remove the food, disassemble the removable equipment, dust.
- 2 Dry clean all internal surfaces. Concrete floor: remove manure, scrape and sweep the floor.
- ⚠ For dirt floors, the litter is removed after washing, in order to absorb the sprayed water. In this case, then strip the bases.

Step 02

CLEANING « Houses and equipment »



- 3 **Soaking** . Presoak all surfaces with clean water at low pressure to soften organic matter.
- 4 **Scouring** . Scour the surfaces with a high-pressure pump (100 bars) for remove dirt, favoring the water flow (instead of too high pressure which damage the surfaces).
- 5 **Foaming** . Soak all surfaces with **DT FOAM®**: 2 L for 100 L of water. Apply with a foam sprayer. Improved quality of washing and disinfection (leave on for 15 to 30 minutes)
- 6 **Rinsing** . Complete rinsing of all surfaces with the high pressure pump

Step 03

DISINFECTION BY SPRAYING We only disinfect clean surfaces!



- 7 **Disinfection** Disinfect all access corridors and the dock by spraying or foaming with a foam sprayer. **PROPHYL® S**: 2 L for 100 L of water > EFFECTIVE ON CRYPTO-COCCI.

Step 04

SANITARY BREAK 24 to 48 hours - The barn must be dry

Step 05

SANITARY BARRIERS



- 8 **Footdips** **PROPHYL® S**: 200 ml in 10 L of water
- 9 **Insecticide** First use a larvicide (80% of fly problems) for application on litter or slurry then complete with an adulticide for application on surfaces
- 10 **Dératiser** Rats, mice "disease vectors"
- 11 **Silos** Washing and cleaning (same as building surface) or dry fumigation (smoke candle)

Before to start with the new flock

LITTER

- 12 **Litter disinfection** In case of poor litter quality: **PROPHYL S® S** at 2%; Spray the solution at the rate of 100 ml / sqm.